



SIEMENS

NAHDI BMS GRAPHICS

Conceptual Graphics Pack – All Systems

Desigo CC | Operational visualization baseline for supplier development

This PDF is a conceptual graphic/wireframe pack, not a final Desigo CC implementation. It translates the approved design philosophy into page-level visual concepts for every system identified in the supplier submission.

Standard right-side structure: SYSTEM INFORMATION ® SELECTED ASSET DETAILS ® ACTIVE ALARMS. System visualization remains specific to the nature of the system



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

DASHBOARD OVERVIEW

Last Updated: 10:25 AM



SYSTEM HEALTH BY CATEGORY

	Normal	Warning	Alarm	Offline	Health
Electrical Systems	95	3	1	0	95%
Mechanical Systems	88	5	2	1	91%
Medical Equipment	97	1	1	0	96%
Building Technology	92	4	2	1	92%
IT Infrastructure	98	1	0	0	99%

View All Systems

ACTIVE ALARMS (17)

View All Alarms


Time	City	Site	System	Asset / Point	Alarm	Priority
10:21 AM	Jeddah	Alsamer Clinics C03JED	UPS	UPS-01	Battery High Temperature	High
10:15 AM	Riyadh	Munisyah Clinics	HVAC / Split AC	AC-TR03	Room Temperature High	High
09:58 AM	Dammam	Istishafa Clinics	Power MDB	MDB-01 / Fdr-07	Feeder Overload	Medium
09:42 AM	Jeddah	Alsamer Clinics C03JED	Fridges TMS	MR-01	Temperature High	Medium
09:33 AM	Makkah	Makkyah Clinics	CCTV System	NVR-02	Storage Usage High	Medium

SITE HEALTH OVERVIEW

View All Sites

Site	City	Normal	Warning	Alarm	Offline	Health
Alsamer Clinics C03JED	Jeddah	45	2	1	0	94%
Munisyah Clinics	Riyadh	38	3	0	1	92%
Istishafa Clinics	Dammam	41	1	2	0	90%
Makkyah Clinics	Makkah	39	0	0	0	100%
Jazan Clinics	Jazan	33	1	1	0	94%

REGIONAL / CITY HEALTH



ALARM TREND (LAST 7 DAYS)



SYSTEM AVAILABILITY



MAINTENANCE DUE

View All

HVAC Preventive Maintenance Munisyah Clinics	25 Feb 2026	Due in 2 days
UPS Battery Test Istishafa Clinics	27 Feb 2026	Due in 4 days
Generator Service Makkyah Clinics	01 Mar 2026	Due in 6 days
TMS Calibration Alsamer Clinics C03JED	05 Mar 2026	Due in 10 days

QUICK ACTIONS

All Alarms View All Active Alarms	System Summary View All Systems Status	Site Overview View All Sites Status	Trend Analysis View Trends & Reports	Reports Generate Reports	Maintenance Maintenance Schedule	Settings Dashboard Settings
--------------------------------------	---	--	---	-----------------------------	-------------------------------------	--------------------------------



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

MDB STATUS

MDB Overall Status	Normal
Incoming Supply	Normal
Busbar Status	Normal
Total Active Load	68%
Power Quality	Normal
System Alarms	1

TOTAL ACTIVE LOAD



TOTAL APPARENT POWER
1,800 kVA

TOTAL ACTIVE ENERGY (TODAY)
8,452 kWh

POWER QUALITY

Normal
THD: 2.1% | PF: 0.98

VOLTAGE SUMMARY (AVG)

L1-L2	414 V
L2-L3	415 V
L3-L1	413 V
L-N (Avg)	239 V

CURRENT SUMMARY (TOTAL)

L1	1,725 A
L2	1,707 A
L3	1,698 A
Neutral	48 A

POWER SUMMARY (TOTAL)

Active Power	1,224 kW
Apparent Power	1,800 kVA
Reactive Power	1,320 kVAr
Power Factor	0.98

ENERGY SUMMARY (TODAY)

Active Energy	8,452 kWh
Reactive Energy	6,105 kVArh
Apparent Energy	10,285 kVAh

DEMAND SUMMARY

Max Demand	1,310 kW
At	09:15 AM
Load Factor	0.78

QUICK ACTIONS (BMS CONTROL)

Open All Feeders

Close All Feeders


Reset Alarms

Sync Energy Meters

Export Report

MDB SINGLE LINE DIAGRAM

View: Single Line



SYSTEM INFORMATION

System Type	Main Distribution Board (MDB)
Manufacturer	Schneider Electric
Model	PrismaSeT P
Rated Voltage	415 V, 50 Hz
Busbar Rating	2500 A
Short Circuit Rating	65 kA
Installation Date	15 Feb 2024
Location	Electrical Room (First Floor)

SELECTED FEEDER DETAILS

Feeder ID	FEEDER-4
Feeder Name	LIFTS
Breaker ID	ACB-04
Breaker Rating	400 A
Status	Closed
Load	69% (110 kW)
Voltage (L-L)	414 V
Current	160 A
Power Factor	0.95
Energy (Today)	1,024 kWh
Connected To	Lift Panel LP-01

ACTIVE ALARMS (1)

View All

Time	Site	System	Alarm	Priority
10:21 AM	Alsamer C03JED	MDB	Feeder-7 Trip	High

VIEW ALL ALARMS

BMS can monitor and control MDB breakers. Ensure all operations are performed as per approved SOP and safety procedures.



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

STATUS

UPS Status	Online
Operating Mode	Normal Mode
Bypass Status	Normal
Battery Status	Normal
Rectifier Status	Normal
Inverter Status	Normal
System Temperature	24.5 °C

LOAD



45 %

135 kW / 300 kVA

BATTERY STATUS



100 %

540 VDC

RUNTIME REMAINING



45 MIN

AT CURRENT LOAD


OUTPUT STATUS



NORMAL

230/400 VAC

UPS SYSTEM OVERVIEW



LEGEND

—	Normal Power
- - -	Bypass
—	No Power
- - -	Fault

INPUT DETAILS

Phase Voltage (L1)	230 V
Phase Voltage (L2)	231 V
Phase Voltage (L3)	230 V
Line Frequency	50.0 Hz
Input Power	142 kW
Input Power Factor	0.99

BATTERY DETAILS

Battery Voltage	540 VDC
Battery Current	12 A
Battery Capacity	100 %
Temperature	25 °C
Charger Status	Float
Health Status	Good

OUTPUT DETAILS

Output Voltage (L1)	230 V
Output Voltage (L2)	230 V
Output Voltage (L3)	230 V
Output Frequency	50.0 Hz
Output Power	135 kW
Output Power Factor	0.98

ENVIRONMENT

UPS Room Temp	
UPS Room	24.5 °C
Humidity	
Status	Normal

QUICK ACTIONS (UPS CONTROL)



Test on Battery



Alarm Silence



Reset Fault



More Actions

UPS INFORMATION



UPS Manufacturer	Siemens
UPS Model	SITOP Modular
UPS Capacity	200 kVA
Serial Number	UPS-01-2024-001
Firmware Version	V2.3.1
Installation Date	15 Feb 2024

ACTIVE ALARMS

3

TIME	ALARM	PRIORITY
10:18:45	Battery High Temperature	High
10:17:12	UPS Overload Warning	Medium
10:15:03	Bypass Input Abnormal	Medium

[VIEW ALL ALARMS](#)



Ensure all operations are performed as per approved SOP and safety procedures.



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System

- Medical Equipment
- Fridge TMS
- Room Pressurization

- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System

- IT Infrastructure
- Smart Rack

FLOOR 01 – LIGHTING STATUS (AT 10:25 AM)

LIGHTING PANEL (LP-01)



Main Breaker ☐ OFF By Schedule

Dimming Level (Floor) 0 %

BMS Control ☒ Enabled

Schedule ☒ Active

Next ON 06:00 AM

Faults / Alarms 0

NORMAL LIGHTING POWER PATH



Normal lighting is OFF by schedule (10:00 PM). Next ON at 06:00 AM.

EMERGENCY POWER PATH



SYSTEM INFORMATION

System Type Lighting Control System

Lighting Panels 3 (One per Floor)

Control Main Breaker ON/OFF (Dry Contact)

Dimming Floor Level Dimming

Normal Lighting Supplied from Lighting Panel

Emergency Lighting ~30% of fixtures

Emergency Supply EDP → EMDB → ATS → MDB / Generator

BMS Schedule Daily (OFF at 10:00 PM, ON at 06:00 AM)

ACTIVE ALARMS (0)

[View All](#)

Time	Zones / Circuit	Alarm	Priority
------	-----------------	-------	----------



No Active Alarms

PANEL SUMMARY

Panel	Location	Circuits	Circuits ON	Circuits OFF	Load (kW)	Load (%)	Status
PANEL – GF	Ground Floor	16	15 (79%)	4 (21%)	8.2		Normal
PANEL – 1F	First Floor	16	12 (75%)	4 (25%)	8.5		Normal
PANEL – 2F	Second Floor	16	11 (85%)	2 (15%)	8.3		Normal
Total		48	38 (79%)	10 (21%)	25.0		Normal



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

GENERATOR STATUS

Generator Overall Status	Normal
Operating Mode	Auto (Standby)
Run Status	Stopped
Load Status	No Load
Alarms	2
Warnings	1

POWER SUMMARY



RUN TIME



NEXT SCHEDULED TEST



FUEL SUMMARY



BATTERY STATUS




COOLANT TEMPERATURE



GENERATOR SYSTEM OVERVIEW

View By: Single Line



ATS DETAILS

Mode	Auto
Position	MAIN
Transfer Time (Main→Gen)	8.2 s
Transfer Time (Gen→Main)	9.1 s
Status	Normal

FUEL SYSTEM

Fuel Level	72 %
Fuel Quantity	720 L
Tank Capacity	1,000 L
Fuel Temperature	28 °C
Status	Normal

ELECTRICAL OUTPUT (GENERATOR)

Voltage (L-L)	0 V
Current	0 A
Frequency	0.0 Hz
Active Power	0 kW
Power Factor	0.00

EXHAUST SYSTEM

Exhaust Temp	180 °C
Back Pressure	12 mbar
Status	Normal

MAINTENANCE

Service Due In	120 h
Next Service Date	10 Jun 2025
Last Service Date	10 Apr 2025
Service Hours	380 h

QUICK ACTIONS

Start Generator

Stop Generator

Test Run

Transfer To Generator

Transfer To Main

Reset Alarms

Mute Alarm

Event Log

More Actions

SYSTEM INFORMATION

Generator ID	GEN-01
Model	Cummins C1000D5
Rated Power	1,000 kVA
Rated Voltage	400 V (3Ph-N)
Serial Number	C1000D5-2023-001
Installation Date	12 Jan 2023

ACTIVE ALARMS

TIME	ALARM	SUBSYSTEM	PRIORITY
10:21:15	Low Fuel Level	Fuel System	High
10:15:34	High Coolant Temp	Engine	Medium

ACTIVE WARNINGS

TIME	WARNING	SUBSYSTEM	PRIORITY
10:18:07	Maintenance Due	Engine	Medium

[VIEW ALL ALARMS & WARNINGS](#)

ENGINE PARAMETERS

Engine Speed	0 RPM
Oil Pressure	4.2 bar
Coolant Temperature	72 °C
Fuel Pressure	3.1 bar
Exhaust Temperature	180 °C
Battery Voltage	28.0 VDC

ENVIRONMENT

Ambient Temperature	29.8 °C
Ambient Humidity	48 %RH
Room Status	Normal



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System

- Medical Equipment
- Fridge TMS
- Room Pressurization

- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System

- IT Infrastructure
- Smart Rack

SYSTEM SUMMARY (FLOOR 02)

	Total Indoor Units	30
	ON	27
	OFF	3
	Total Cooling Load	98.6 kW
	Total Power	75.4 kW
	Average Room Temp.	24.2 °C
	Average Room Humidity	48 %RH

SYSTEM MODE SUMMARY

	Cool	27
	Dry	2
	Fan	1
	Off	3

ENERGY SUMMARY (TODAY)

Energy Consumption	215.4 kWh
Operating Cost	86.2 SAR
Carbon Emission	0.12 Ton

SCHEDULE OVERVIEW

Current Mode	COOLING
Cooling Start	07:00 AM
Cooling Stop	10:00 PM
Cooling Stop	10:00 PM
Next Action	OFF at 10:00 PM
Active Schedule	Weekday Schedule

VIEW / EDIT SCHEDULE

INDOOR UNIT STATUS (FLOOR 02)

Unit ID	Zone / Area	Covered Rooms / Area	Type	Mode	Fair Splice Temp.	Room Temp.	Room Humidity	Status
IU-01	Reception	Reception	Cool	Auto	24.0 °C	24.3 °C	48 %RH	ON
IU-02	Open Office - A	Open Office Area	Cool	Auto	23.5 °C	23.5 °C	47 %RH	ON
IU-03	Meeting Room 1	Meeting Room 1	Cool	Low	24.0 °C	24.2 °C	50 %RH	ON
IU-04	Manager Office	Manager Office	Cassette	Off	--	--	51 %RH	OFF
IU-05	Consulting Room 1	Room 1, Room 2	Cool	Auto	22.0 °C	24.8 °C	47 %RH	ON
IU-06	Consulting Room 2	Room 3, Room 4	Cool	Auto	22.0 °C	24.1 °C	46 %RH	ON
IU-07	Laboratory	Laboratory	Cool	High	23.0 °C	23.4 °C	44 %RH	ON
IU-08	Storage	Storage	Off	--	--	26.1 °C	52 %RH	OFF

Showing 1 to 8 of 30 entries

1 2 3 4 >


OUTDOOR UNIT STATUS (FLOOR 02)

Unit ID	Model	Connected IU	Status	Capacity	Power (kW)
OU-01	AUY4SL	IU-01, IU-02, IU-03	ON	16.0 kW	3.6
OU-02	AUY4SL	IU-04, IU-05, IU-06	ON	16.0 kW	3.4
OU-03	AUY4SL	IU-07, IU-08, IU-09	ON	16.0 kW	3.2
OU-04	AUY4SL	IU-10, IU-11, IU-12	ON	16.0 kW	3.1
OU-05	AUY4SL	IU-13, IU-14, IU-15	ON	16.0 kW	3.3
OU-07	AUY4SL	IU-19, IU-20, IU-21	ON	16.0 kW	3.6
OU-08	AUY4SL	IU-22, IU-23, IU-24, IU-25, IU-26, IU-27, IU-28, IU-29, IU-30	ON	16.0 kW	4.9

Showing 1 to 8 of 8 entries

FLOOR 02 - AC UNIT LAYOUT

View By: System



ON OFF COOL DRY ALARM

SYSTEM DETAILS

System Type	Split System
Refrigerant Type	R410A
Total Indoor Units	30
Total Outdoor Units	8
Total Cooling Capacity	120.0 kW
Total Connected Load	98.6 kW
Total Operating Load	75.4 kW
Average Efficiency (EER)	3.21
Installation Date	Jan 15, 2024

INDOOR UNIT DETAILS

IU-06 – Staff Lounge

Status	ON
Mode	Cooling
Room Temp.	25.5 °C
Setpoint	24.0 °C
Room Humidity	51 %RH
Fan Speed	Auto
Capacity	68 %
Connected Outdoor Unit	OU-02
Served Area	Staff Lounge
Alarm	High Room Temp.

Click anywhere outside to close

SYSTEM STATUS

Refrigerant System	Normal
Power Supply	Normal
Drain System	Normal
Filter Status	Normal
Overall Status	Normal

ACTIVE ALARMS

TIME	ALARM	UNIT	PRIORITY
10:35:12 AM	High Room Temp.	IU-05	Medium
10:28:45 AM	Indoor Unit Off	IU-04	Low

VIEW ALL ALARMS

QUICK ACTIONS

- ALL UNITS ON
- ALL UNITS OFF
- COOL MODE
- DRY MODE
- FAN MODE
- SET ALL TO AUTO
- REFRESH
- DASHBOARD
- ENERGY REPORT
- MORE ACTIONS



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System

- Medical Equipment
- Fridge TMS
- Room Pressurization

- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System

- IT Infrastructure
- Smart Rack

SYSTEM SUMMARY (FLOOR 02)

Total Exhaust Fans	16
ON	13
OFF	3
Total Airflow	8,450 CMH
Total Power	7.6 kW
Average Fan Speed	68 %

SYSTEM MODE SUMMARY

Auto	14
Manual	2
Off	0

ENERGY SUMMARY (TODAY)

Energy Consumption	45.2 kWh
Operating Cost	18.1 SAR
Carbon Emission	0.03 Ton


SCHEDULE OVERVIEW

Current Mode	AUTO
Schedule	Weekday Schedule
Next Change	10:00 PM (OFF)

VIEW / EDIT SCHEDULE

FAN EXHAUST OVERVIEW (FLOOR 02)

View By: System



FAN STATUS

FAN STATUS	Status	Mode	Fan Speed (%)	Airflow (CMH)	Power (kW)	Runtime (Today)	Filter Status
FE-01 Toilet (M)	ON	Auto	65	780	0.55	6.1 h	OK
FE-02 Toilet (F)	ON	Auto	65	780	0.55	6.0 h	OK
FE-03 Pantry	ON	Auto	60	500	0.37	5.8 h	OK
FE-04 Lab	ON	Auto	72	950	0.75	6.3 h	OK
FE-05 Storage	OFF	--	0	0	0.00	0.0 h	--
FE-06 Electrical Room	ON	Auto	68	900	0.75	6.2 h	OK
FE-07 X-Ray Room	ON	Auto	70	850	0.75	6.1 h	OK
FE-08 Pharmacy	ON	Auto	68	850	0.75	6.0 h	OK

FAN STATUS (FLOOR 02)

FAN STATUS (FLOOR 02)	Status	Mode	Fan Speed (%)	Airflow (CMH)	Power (kW)	Runtime (Today)	Filter Status
FE-09 Server Room	ON	Auto	75	1,100	1.10	6.4 h	OK
FE-10 Consult Room 1	ON	Auto	60	500	0.37	5.7 h	OK
FE-11 Consult Room 2	ON	Auto	60	500	0.37	5.6 h	OK
FE-12 Consult Room 3	ON	Auto	60	500	0.37	5.8 h	OK
FE-13 Consult Room 4	OFF	--	0	0	0.00	0.0 h	--
FE-14 Consult Room 5	ON	Auto	60	500	0.37	5.9 h	OK
FE-15 Wash Area	ON	Auto	65	750	0.55	6.0 h	OK
FE-16 Garbage Room	ON	Auto	70	850	0.75	6.1 h	OK

QUICK ACTIONS

- ALL FANS ON
- ALL FANS OFF
- AUTO MODE
- MANUAL MODE
- REFRESH STATUS
- FILTER STATUS
- SCHEDULE
- MORE ACTIONS

SYSTEM DETAILS

System Type	Fan Exhaust
Total Exhaust Fans	16
Total Airflow Capacity	9,800 CMH
Total Connected Load	12.0 kW
Total Operating Load	7.6 kW
Average Fan Speed	68 %
Installation Date	Jan 15, 2024

FAN DETAILS

FE-04 - Lab

Status	ON
Mode	Auto
Fan Speed	72 %
Airflow	950 CMH
Power	0.75 kW
Voltage	230 V
Current	3.2 A
Runtime (Today)	6.3 h
Filter Status	OK
Last Maintenance	10 Jan 2025

Click anywhere outside to close

SYSTEM STATUS

Fan Control Panel	Normal
Power Supply	Normal
VFD System	Normal
Filter Status	Normal
Overall Status	Normal

ACTIVE ALARMS

TIME	ALARM	UNIT	PRIORITY
10:18:07 AM	Filter Dirty	FE-13	Medium

VIEW ALL ALARMS



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System

- Medical Equipment
- Fridge TMS
- Room Pressurization

- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System

- IT Infrastructure
- Smart Rack

WATER TANKS

View By: Group

TANKS SUMMARY

	Total Tanks	4
	Normal	3
	Low Level	1
	Over Flow	0
	Offline	0

WATER SUMMARY (ALL TANKS)

Total Capacity	118,000 L
Current Volume	86,500 L
Overall Level	73 %



WATER QUALITY (OVERALL)

Chlorine Residual	0.65 ppm
pH	7.2
TDS	210 ppm


PUMPING STATUS

	Booster Pumps	2 / 2 Running
	Transfer Pumps	1 / 1 Running

TANKS STATUS LIST

Tank ID	Tank Name	Type	Location	Capacity (L)	Current Volume (L)	Level (%)	Status	Last Update
T-01	Fire Tank	Fire	UG Floor	90,000	81,000	90	Normal	10:25:10 AM
T-02	Domestic Tank	Domestic	UG Floor	20,000	14,400	72	Normal	10:25:08 AM
T-03	Flushing Tank	Flushing	UG Floor	8,000	2,240	28	Low Level	10:24:58 AM
T-04	RO Tank	Treated Water	UG Floor	10,000	7,600	76	Normal	10:25:09 AM

TANKS OVERVIEW



SYSTEM INFORMATION

System Type	Water Storage System
Total Tanks	4
Total Capacity	118,000 L
Current Volume	86,500 L
Last Update	10:25:12 AM
System Status	Normal

SELECTED TANK DETAILS

T-03 - FLUSHING TANK (UG)


Status	Low Level
Capacity	8,000 L
Current Volume	2,240 L
Level	28 %
Low Level Setpoint	30 %
High Level Setpoint	90 %
Inlet Source	Domestic Tank
Outlet Destination	Building Distribution
Last Update	10:24:58 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Alarm	Tank ID	Priority
10:24:47 AM	Low Level	T-03	Medium

VIEW ALL ALARMS

LEVEL TREND (ALL TANKS)



TANK QUICK INFO

Total Capacity 118,000 L	Current Volume 86,500 L	Average Level 73 %
Lowest Level Tank T-03 (28 %)	Highest Level Tank T-01 (90 %)	Tanks Normal 3 / 4



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

ELEVATOR SUMMARY

Total Elevators	3
Running	2
In Use	1
Out of Service	0
Offline	0

OPERATION SUMMARY (TODAY)

Total Trips (Today)	46
Total Passengers (Today)	218
Average Waiting Time	18 sec
Availability	99.7 %

SYSTEM STATUS

Communication	Normal
Controller Status	Normal
Door Operation	Normal
Safety Circuit	Normal
Power Supply	Normal

ELEVATOR STATUS LIST

Elevator ID	Type	Status	Current Floor	Direction	Load	Passengers	Last Update
EL-01	Passenger	Running	2	Up	300 kg (30%)	0	10:25:10 AM
EL-02	Passenger	In Use	5	Down	650 kg (65%)	2	10:25:08 AM
EL-03	Service	Running	G	Up	250 kg (25%)	0	10:25:09 AM

Showing 1 to 3 of 3 entries

ELEVATOR STATUS OVERVIEW

EL-01

Passenger Elevator

RUNNING

2

Floor

Up

Idle

Load: 300 kg (30%)

Running

EL-02

Passenger Elevator

IN USE

5

Floor

Down

Passengers

Load: 650 kg (65%)

In Use

EL-03

Service Elevator

RUNNING

G

Floor

Up

Idle

Load: 250 kg (25%)

Running

FLOORS

- R
- 2
- 1
- M
- G
- B

SYSTEM INFORMATION

System Type	Elevator System
Total Elevators	3
Total Stops	6 Floors (B + R)
Control System	Schindler 5500
Rated Load (Max)	1,000 kg
Last Update	10:25:12 AM
System Status	Normal

SELECTED ELEVATOR DETAILS

EL-02 – Passenger Elevator	
Status	In Use
Current Floor	5
Direction	Down
Load	650 kg (65%)
Passengers	2
Door Status	Closed
Speed	1.0 m/s
Last Service	20 Feb 2026
Run Hours	1,256 h
Last Update	10:25:08 AM

ACTIVE ALARMS (THIS SYSTEM)


Time	Alarm	Elevator ID	Priority
No Active Alarms			
VIEW ALARMS HISTORY			

ELEVATOR INFO

- Passenger Elevator**
Used for general passenger transportation.
- Service Elevator**
Used for service and goods transportation.

Note
Elevator control is not enabled in the current phase.
Monitoring only.

PERFORMANCE TREND (TODAY)





Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator
- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System
- Medical Equipment
- Fridge TMS
- Room Pressurization
- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System
- IT Infrastructure
- Smart Rack

FIRE ALARM SYSTEM OVERVIEW

SYSTEM SUMMARY

Overall Status	Normal
System Mode	Auto
Total Loops	2
Total Detectors	86
Total Manual Call Points	12
Total Sounders	18
Normal	86
Fault	0
Alarm	0
Disabled / Bypass	0
Offline	0


ZONE SUMMARY

Total Zones	12
Normal	12
Alarm	0
Fault	0
Disabled / Bypass	0

SYSTEM STATUS

FACP (Control Panel)	Normal
Booster Panel (Reception)	Normal
AC Power	Normal
Battery	Normal
Communication	Normal
Ground Fault	Normal

Loop / SLC
NAC / Output
Network / Communication



FSS PANEL STATUS (10)

No.	FSS Panel	Location	Run Status	Fault Status	Common Alarm	Last Update
1	AFSS-01	Server Room	Normal	Normal	Normal	10:25:08 AM
2	AFSS-02	Pharmacy	Normal	Normal	Normal	10:25:10 AM
3	AFSS-03	Laboratory	Normal	Normal	Normal	10:25:12 AM
4	AFSS-04	Consultation Rooms	Normal	Normal	Normal	10:25:14 AM
5	AFSS-05	Reception & Lobby	Normal	Normal	Normal	10:25:16 AM
6	AFSS-06	Corridor - 1	Normal	Normal	Normal	10:25:18 AM
7	AFSS-07	Corridor - 2	Normal	Normal	Normal	10:25:20 AM
8	AFSS-08	Utility Room	Normal	Normal	Normal	10:25:22 AM
9	AFSS-09	Staff Area	Normal	Normal	Normal	10:25:24 AM
10	AFSS-10	External Area	Normal	Normal	Normal	10:25:26 AM

View By: System

SYSTEM INFORMATION

System Type	Fire Alarm System
Total Capacity	2 Loops
Installed Power	230 VAC
Operating Mode	Auto
Last Update	10:25:12 AM
System Status	Normal

SELECTED DEVICE DETAILS

● FACP-01 – Fire Alarm Control Panel	
Manufacturer	Simplex
Model	4100ES
Loops	2
Location	Control Room
Status	Normal
AC Power	Normal
Battery	Normal
Last Test	15 Feb 2026 09:15 AM
Last Update	10:25:08 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Zone / Device	Alarm	Priority
------	---------------	-------	----------

No Active Alarms

VIEW ALARMS HISTORY

QUICK ACTIONS

Silence Buzzer

Reset System

Evacuate

Drill Mode

Test Lamps

System Report

More Actions

Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

FIRE PUMP SYSTEM

View By: System

SYSTEM SUMMARY

Overall Status	Normal
Operating Mode	Auto
Total Pumps	3
Running	2
Standby	1
Fault / Alarm	0
Offline	0

OPERATION SUMMARY

System Pressure	6.2 bar
Discharge Pressure	6.1 bar
Jockey Pressure	6.3 bar
Flow Rate	0.0 m³/h
Fire Pump Demand	No
Water Temperature	26.4 °C

POWER & CONTROLLER STATUS


Main Supply	Normal
Controller Status	Normal
Battery Charger	Normal
Communication	Normal

PUMP STATUS LIST

Pump ID	Pump Name	Type	Status	Mode	Speed (RPM)	Run Time (Today)	Last Update
FP-01	Main Pump 1	Main	Running	Auto	1750	1 h 35 m	10:24:58 AM
FP-02	Main Pump 2	Main	Running	Auto	1760	1 h 20 m	10:24:52 AM
FP-03	Jockey Pump	Jockey	Standby	Auto	0	-	10:24:45 AM

Showing 1 to 3 of 3 entries

SYSTEM OVERVIEW


SYSTEM PRESSURE
6.2 bar

TO SPRINKLER NETWORK

TEST HEADER

FP-01
MAIN PUMP 1

RUNNING

FP-02
MAIN PUMP 2

RUNNING

FP-03
JOCKEY PUMP

STANDBY

DISCHARGE HEADER


DRAIN

DISCHARGE PRESSURE
6.1 bar

Suction Discharge Open Closed

PRESSURE & FLOW TREND (TODAY)

View By: Pressure



SYSTEM INFORMATION

System Type	Fire Pump System
Total Pumps	3
Main Pumps	2
Jockey Pump	1
Total Capacity	150 m³/h @ 9.0 bar
Installed Power	55.0 kW
Control Mode	Auto
Last Update	10:25:12 AM
System Status	Normal

SELECTED PUMP DETAILS

FP-01 - MAIN PUMP 1	Running
Status	Running
Mode	Auto
Speed	1750 RPM
Flow Rate	0.0 m³/h
Discharge Pressure	6.1 bar
Suction Pressure	2.3 bar
Motor Current	18.6 A
Power	18.2 kW
Run Time (Today)	1 h 35 m
Last Start	08:49:12 AM
Last Update	10:24:58 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Alarm	Pump ID	Priority
------	-------	---------	----------

No Active Alarms

VIEW ALARMS HISTORY

QUICK INFO

Pump Test Schedule	Controller Panel	Flow Switch Status	Pressure Switch Status
Maintenance Log	System Settings	Cause & Effect Status	More Actions



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System

- Medical Equipment
- Fridge TMS
- Room Pressurization

- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System

- IT Infrastructure
- Smart Rack

SYSTEM SUMMARY

Overall Status	Normal
Operating Mode	Auto
Total RO Units	2
RO Tanks	2
Softener Units	2
Running	4
Standby	0
Fault / Alarm	0
Offline	0

WATER QUALITY (AT RO OUTLET)


TDS	18 ppm
pH	7.1
Hardness	3 ppm
Turbidity	< 1 NTU
Temperature	24.6 °C

Quality Status: Good

ASSET STATUS LIST

Asset ID	Asset Name	Type	Status	Mode	Flow Rate (m³/h)	Last Update
ST-01	Softener 1	Softener	Running	Auto	-	10:25:10 AM
ST-02	Softener 2	Softener	Running	Auto	-	10:25:08 AM
RO-01	RO Unit 1	RO Unit	Running	Auto	1.2	10:24:58 AM
RO-02	RO Unit 2	RO Unit	Running	Auto	1.1	10:24:57 AM
RT-01	RO Tank 1	RO Tank	Normal	-	-	10:25:05 AM
RT-02	RO Tank 2	RO Tank	Normal	-	-	10:25:06 AM

SYSTEM OVERVIEW



SYSTEM INFORMATION

System Type	RO Softener & RO Tank System
Total Capacity	2.0 m³/h
Installed Power	6.5 kW
Operating Mode	Auto
Last Update	10:25:12 AM
System Status	Normal

SELECTED ASSET DETAILS

RO-01 - RO Unit 1	
Status	Running
Flow Rate	1.2 m³/h
Recovery Rate	65 %
Inlet Pressure	3.2 bar
Outlet Pressure	2.1 bar
Feed TDS	210 ppm
Outlet TDS	18 ppm
Temperature	24.4 °C
Run Time (Today)	3 h 42 m
Last Service	15 Feb 2026
Last Update	10:24:58 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Alarm	Asset ID	Priority
------	-------	----------	----------

No Active Alarms

[VIEW ALARMS HISTORY](#)

QUICK INFO

System Schematic

Water Quality Report

Filter DP Status

RO Performance

Tank Level Report

More Actions



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System

- Medical Equipment
- Fridge TMS
- Room Pressurization

- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System

- IT Infrastructure
- Smart Rack

FRIDGE MONITORING SUMMARY

Total Refrigerators	24
Normal (In Range)	21
Warning (Near Limit)	1
Alarm (Out of Range)	2
Offline	0
Highest Temperature	8.7 °C
Lowest Temperature	1.4 °C

STATUS DISTRIBUTION




FLOOR SELECTION

Floor 02

Click on any refrigerator on the layout or select from the list below to view details and trends.

FRIDGE MONITORING OVERVIEW – FLOOR 02

View By: System



Normal (In Range) Warning (Near Limit) Alarm (Out of Range) Offline

MEDICATION REFRIGERATOR STATUS LIST (FLOOR 02)

Sensor ID	Location / Area	Temperature (°C)	Temp. Range (°C)	Humidity (%RH)	Hum. Range (%RH)	Status	Last Update
MR-01	LAB	8.7	2.0 – 8.0	51	30 – 60	ALARM (High Temp.)	10:42:15 AM
MR-02	TRIAGE	4.1	2.0 – 8.0	47	30 – 60	NORMAL	10:42:12 AM
MR-03	STORE	6.2	2.0 – 8.0	48	30 – 60	WARNING	10:42:10 AM

Showing 1 to 3 of 3 entries

SYSTEM INFORMATION

System Type	Temperature & Humidity Monitoring
System Name	Medication Refrigerators
Floor / Area	Floor 02
Total Sensors	24
Network	BMS-MED-TH
Last Update	10:42:30 AM
System Status	Normal

SELECTED SENSOR DETAILS

MR-01 – LAB	
Status	ALARM (High Temperature)
Temperature	8.7 °C
Temperature Range	2.0 – 8.0 °C
Humidity	51 %RH
Humidity Range	30 – 60 %RH
Alarm	High Temperature
Alarm Since	10:32:18 AM
Alarm Duration	00:10:12
Sensor Status	Normal
Last Update	10:42:15 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Sensor ID	Alarm	Value	Priority
10:32:18 AM	MR-01	High Temp.	8.7 °C	High
10:12:07 AM	MR-03	High Temp.	6.2 °C	Medium

VIEW ALL SYSTEM ALARMS

NOTES

- All temperature and humidity readings are from calibrated sensors.
- Ranges are configurable per refrigerator type.



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator

- Mechanical Systems
 - HVAC / Split AC
 - Fan Exhaust
 - Water Tanks
 - Elevator
 - Fire Alarm
 - Fire Pump
 - Water Softener & RO System

- Medical Equipment
 - Fridge TMS
 - Room Pressurization

- Building Technology
 - Access Control System
 - CCTV System
 - Public Address System
 - Nurse Call System

- IT Infrastructure
 - Smart Rack

ROOM PRESSURIZATION SUMMARY

Total Pressurized Rooms	2
Normal	2
Warning	0
Alarm	0
Offline	0

PRESSURE SUMMARY

Rooms with Negative Pressure	2
Rooms with Normal Pressure	0
Rooms with Pressure Alarm	0

ENVIRONMENT SUMMARY

Average Room Temperature	22.8 °C
Average Room Humidity	48 %RH
Average Differential Pressure	-5.8 Pa


FLOOR SELECTION

Floor 02

Click on any room on the layout or select from the list below to view details and trends.

ISOLATION ROOM MONITORING – FLOOR 02

View By: System



Airflow Direction Normal (Negative Pressure) Warning (Near Limit) Alarm (Pressure Failure) Offline

ROOM PRESSURIZATION STATUS LIST (FLOOR 02)

Room ID	Room Name	Location / Area	Temperature (°C)	Humidity (%RH)	Differential Pressure (Pa)	Status	Last Update
IR-01	Isolation Room	Floor 02	22.6	48	-6.2	Normal	10:25:10 AM
MB-01	Microbiology Room (LAB)	Floor 02 – LAB	23.1	47	-5.4	Normal	10:25:08 AM

Showing 1 to 2 of 2 entries

SYSTEM INFORMATION

System Type	Room Pressurization
System Name	Room Pressurization
Floor / Area	Floor 02
Total Pressurized Rooms	2
Network	BMS-RP-MON
Last Update	10:25:10 AM
System Status	Normal

SELECTED ROOM DETAILS

IR-01 – Isolation Room

Status	Normal
Room Type	Isolation Room
Temperature	22.6 °C
Temperature Range	20.0 – 24.0 °C
Humidity	48 %RH
Humidity Range	30 – 60 %RH
Differential Pressure	-6.2 Pa
Pressure Setpoint	≤ -2.5 Pa
Air Changes (ACH)	12 ACH
Sensor Status	Normal
Last Update	10:25:10 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Room ID	Alarm	Value	Priority
------	---------	-------	-------	----------

No Active Alarms

VIEW ALARMS HISTORY

NOTES

- All pressure values are relative to corridor pressure.
- Negative pressure is required to prevent cross contamination.
- Temperature and humidity ranges are configurable per room type.



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

ACCESS CONTROL SUMMARY

	Total Controllers	7
	Total Doors	28
	Total Floors	3
	Doors per Controller (Avg.)	4
	Controller Location	IDF
	Interface Type	Dry Contact
	BMS Integration	Monitoring Only
	ACS Platform	BIS

CONTROLLER STATUS

	Normal	7
	Interface Alarm	0
	Fault	0
	Communication Loss	0

SYSTEM STATUS

Interface		Normal
Controllers		Normal
Power Supply		Normal (230 VAC)

NOTE

This screen provides monitoring information only. Control of doors, locks and access is not available in BMS (Dry Contact interface only).

ACCESS CONTROL SYSTEM OVERVIEW


View By: System

CONTROLLERS 7 7 Normal	DOORS 28 View Doors	FLOORS 3 View Floors	INTERFACE TYPE Dry Contact Monitoring Only	INTERFACE POINTS 28 All Normal
------------------------------	---------------------------	----------------------------	--	--------------------------------------

FLOOR / AREA VIEW

Ground Floor

Legend: Controller Location (IDF) Door (4 per Controller) Controller Connection (Dry Contact)



CONTROLLER OVERVIEW

Controller ID	Location (IDF)	Floor	Doors	Status	Last Update
CTRL-01	IDF-GF	GF	4	Normal	10:25:08 AM
CTRL-02	IDF-GF	GF	4	Normal	10:25:07 AM
CTRL-03	IDF-GF	GF	4	Normal	10:25:09 AM
CTRL-04	IDF-1F	1F	4	Normal	10:25:06 AM
CTRL-05	IDF-1F	1F	4	Normal	10:25:07 AM
CTRL-06	IDF-2F	2F	4	Normal	10:25:06 AM
CTRL-07	IDF-2F	2F	4	Normal	10:25:06 AM

View all controllers

INTERFACE POINT SUMMARY

Interface Type	Total Points	Normal	Alarm	Last Update
Dry Contact (DI)	28	28	0	10:25:06 AM

FLOOR SUMMARY

Floor	Controllers	Doors	Status
Ground Floor (GF)	3	12	Normal
First Floor (1F)	2	8	Normal
Second Floor (2F)	2	8	Normal

View all floors

SYSTEM INFORMATION

System Type	Access Control System
ACS Platform	BIS
BMS Interface	Dry Contact
BMS Integration	Monitoring Only
Total Controllers	7
Total Doors	28
Total Floors	3
Installed Power	230 VAC
Operating Mode	Auto
Last Update	10:25:12 AM
System Status	Normal

SELECTED DOOR / ACCESS POINT

D-03 - Pharmacy Entrance

Floor	Ground Floor
Location	Pharmacy
Controller	CTRL-01
Controller Location	IDF-GF
Controller Port	PORT-03
Door Type	Single Door
Interface Type	Dry Contact
BMS Point (DI)	DI-CTRL01-D03
BMS Monitoring	Available
Door Status	Not Available
Lock Status	Not Available
Access Events	Not Available
Door Control	Not Available
Last Update	10:25:08 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Zone / Device	Alarm	Priority
------	---------------	-------	----------

No Active Alarms

VIEW ALARMS HISTORY

QUICK ACTIONS

Controller List	Door / Point List	Floor Map	Interface Status
Maintenance Info	Asset Information	Reports	More Actions



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

CCTV SUMMARY

Total Cameras	86
Indoor Cameras	68
Outdoor Cameras	18
Dome Cameras	56
Bullet Cameras	30
Total NVRs	2
Total Storage Capacity	24 TB
Total Floors	3

Online Cameras	83
Disconnected Cameras	3

SYSTEM STATUS

NVR-01	Online
NVR-02	Online
Network	Normal
Recording	Normal
Last Update	10:25:12 AM

CAMERA STATUS



CCTV SYSTEM OVERVIEW

View By: System

NVRs 2 View Details	Cameras 86 View Details	Indoor / Outdoor 68 / 18 View Details	Dome / Bullet 56 / 30 View Details	Storage Capacity 24 TB View Details
---------------------------	-------------------------------	---	--	---

FLOOR / AREA VIEW

Ground Floor Mezzanine Floor First Floor

ALSAMER CLINICS (C03JED) - GROUND FLOOR



LEGEND

Dome (Indoor) Bullet (Indoor) Bullet (Outdoor) Disconnected Camera NVR Location Network Connection Camera Connection

Note: Camera locations are based on shop drawings and may be updated during renovation.

NVR OVERVIEW

NVR Name	IP Address	Channels	Storage	Recording Status	Uptime	Last Update	Status
NVR-01	10.10.10.101	64	12 TB	Recording	15d 06:24:33	10:25:12 AM	Online
NVR-02	10.10.10.102	64	12 TB	Recording	11d 03:17:06	10:25:12 AM	Online

Showing 1 to 2 of 2 entries

SYSTEM INFORMATION

System Type	CCTV System
Manufacturer	Hanwha (Wisenet)
Platform	Wisenet WAVE
Total Cameras	86
Total NVRs	2
Total Storage Capacity	24 TB
Monitoring	Real-time via SNMP
Last Update	10:25:12 AM
System Status	Normal

SELECTED CAMERA DETAILS

CAM-0032 (Online)	
Location	Ground Floor - Reception
Camera Type	Dome (Indoor)
Resolution	4MP (2688x1520)
IP Address	10.10.10.32
NVR	NVR-01
Channel	CH-32
Status	Online
Firmware Version	V2.10.1
Last Update	10:25:12 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Device	Alarm	Priority
No Active Alarms			
VIEW ALARMS HISTORY			

QUICK ACTIONS

Camera List	NVR List	Camera Map	Interface Status
Recording Status	Storage Status	Maintenance Info	Reports



Dashboard

Electrical Systems

Power MDB

Building UPS

Lighting

Generator

Mechanical Systems

HVAC / Split AC

Fan Exhaust

Water Tanks

Elevator

Fire Alarm

Fire Pump

Water Softener & RO System

Medical Equipment

Fridge TMS

Room Pressurization

Building Technology

Access Control System

CCTV System

Public Address System

Nurse Call System

IT Infrastructure

Smart Rack

PUBLIC ADDRESS SUMMARY

	Total Zones	12
	Active Zones	12
	Amplifiers	2
	Speakers	96
	Microphone Stations	3

	Normal	12
	Fault	0
	Offline	0

SYSTEM STATUS

	PA Controller	Normal
	Amplifier 01	Normal
	Amplifier 02	Normal
	Network	Normal
	Power Supply	Normal

MICROPHONE STATIONS

	1 Main Reception	Online
	2 ER Reception	Online
	3 Control Room	Online

NOTE

- This Public Address system is used for paging, announcements and emergency evacuation.
- System is monitored via dry contact interface only.


PUBLIC ADDRESS SYSTEM OVERVIEW

	ZONES		SPEAKERS		AMPLIFIERS		MICROPHONE STATIONS		MESSAGE TYPES
	12		96		2		3		5
	12 Active		View Details		View Details		View Details		View Messages

ZONE QUICK SELECT

1 Ground Floor	2 Mezzanine Floor	3 First Floor	4 Annex Floor	5 Clinics Rooms	6 Technical Rooms	7 Stairs Cases
----------------	-------------------	---------------	---------------	-----------------	-------------------	----------------

ALSAMER CLINICS (C03JED) – GROUND FLOOR




Note: Speaker locations are based on shop drawings and may be updated during renovation.

ZONE STATUS LIST

Zone No.	Zone Name	Speakers	Status	Last Update
1	Ground Floor	13	Normal	10:25:08 AM
2	Mezzanine Floor	0	Normal	10:25:07 AM
3	First Floor	0	Normal	10:25:09 AM
4	Annex Floor	0	Normal	10:25:07 AM
5	Clinics Rooms	0	Normal	10:25:06 AM

[View all zones](#)

BROADCAST / SYSTEM TREND (TODAY)



SYSTEM INFORMATION

System Type	Public Address System
Manufacturer	TOA
Platform	VM-3000
Total Zones	12
Total Speakers	96
Amplifiers	2
Total Output Power	220 W
Interface to BMS	Monitoring Only
BMS Monitoring Points	Loop / Amplifier Level
Last Update	10:25:12 AM
System Status	Normal

SELECTED ZONE DETAILS

1 Ground Floor	
Zone Number	1
Zone Name	Ground Floor
Speaker Type	Ceiling (10W)
Speaker Quantity	13
Total Power	130 W
Available Power Taps	78 W
Amplifier Channel(s)	CD#1 - CD#2 (NEO4)
Amplifier	Amplifier 01
Status	Normal
Last Update	10:25:12 AM

ACTIVE ALARMS (THIS SYSTEM)

Time	Zone / Device	Alarm	Priority
No Active Alarms			
VIEW ALARMS HISTORY			

QUICK INFO

Zone Status	Amplifier Status	Speaker Status
Emergency Broadcast	System Health	Event History



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator
- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System
- Medical Equipment
- Fridge TMS
- Room Pressurization
- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System
- IT Infrastructure
- Smart Rack

NURSE CALL SUMMARY

Total Call Points	6
Active Calls	2
Emergency Calls	1
Normal Calls	1
Nurse Stations	1

View Details

SYSTEM STATUS

Nurse Call Controller	Normal
Panels / Gateways	Normal
Network	Normal
Power Supply	Normal
Nurse Station 1	Normal

CALL STATUS SUMMARY



NURSE STATION STATUS


Nurse Station 1	Online
-----------------	--------

NURSE CALL SYSTEM OVERVIEW

CALL POINTS 6 View Details	ACTIVE CALLS 2 View Details	EMERGENCY CALLS 1 View Details	NORMAL CALLS 3 View Details	NURSE STATIONS 1 View Details
----------------------------------	-----------------------------------	--------------------------------------	-----------------------------------	-------------------------------------

FLOOR / AREA VIEW

Ground Floor



LEGEND

Normal Call	Active Call	Emergency Call	Nurse Station	Non-Monitored Area
-------------	-------------	----------------	---------------	--------------------

Note: Call point locations are based on shop drawings and may be updated during renovation.

NURSE CALL STATUS LIST

Point ID	Location	Call Type	Status	Last Update
ER-05	Obs. Female - Bed 05	Emergency (Pull Cord)	Active	10:25:08 AM
ER-12	Obs. Female - Bed 12	Call Button	Active	10:25:07 AM
ER-02	Obs. Male - Bed 02	Call Button	Normal	10:25:06 AM
ER-07	Pan Room - Bed 07	Call Button	Normal	10:25:03 AM
ER-15	Obs. Male - Bed 15	Call Button	Normal	10:25:02 AM
ER-10	Obs. Female - Bed 10	Call Button	Normal	10:24:58 AM

Showing 1 to 6 of 6 entries

CALLS / EVENTS (RECENT)

Time	Event	Point ID	Location	Type	Priority
10:25:08 AM	Call Activated	ER-05	Obs. Female - Bed 05	Emergency (Pull Cord)	High
10:25:07 AM	Call Activated	ER-12	Obs. Female - Bed 12	Call Button	Medium
10:25:06 AM	Call Cleared	ER-03	Obs. Male - Bed 03	Call Button	Low
10:24:45 AM	Call Activated	ER-15	Obs. Male - Bed 15	Call Button	Low
10:24:28 AM	Call Cleared	ER-06	Obs. Female - Bed 06	Call Button	Low

Showing 1 to 5 of 15 entries

View all events

SYSTEM INFORMATION

System Type	Nurse Call System
Manufacturer	ZKR
System Model	ZKR-9200
Installation Date	Jan 10, 2026
Total Call Points	6
Total Nurse Stations	1
System Status	Normal

SELECTED CALL POINT DETAILS

ACTIVE CALL	
Point ID	ER-05
Location	Observation Female - Bed 05
Floor / Area	Ground Floor
Call Type	Emergency (Pull Cord)
Status	Active
Nurse Station	Nurse Station 1
Controller / Panel	ZKR-9200
Priority	High
Time Since	00:01:24

ACKNOWLEDGE CALL

ACTIVE ALARMS (1)

Time	Point ID	Location	Call Type	Priority	Status
10:24:15 AM	ER-05	Obs. Female - Bed 05	Emergency	High	Active

VIEW ALL ALARMS

QUICK INFO

Call Point Status	Nurse Station Status	System Health
Event History	Emergency Broadcast	Configuration Info



Dashboard

- Electrical Systems
- Power MDB
- Building UPS
- Lighting
- Generator
- Mechanical Systems
- HVAC / Split AC
- Fan Exhaust
- Water Tanks
- Elevator
- Fire Alarm
- Fire Pump
- Water Softener & RO System
- Medical Equipment
- Fridge TMS
- Room Pressurization
- Building Technology
- Access Control System
- CCTV System
- Public Address System
- Nurse Call System
- IT Infrastructure
- Smart Rack

SMART RACK SYSTEM OVERVIEW

RACK STATUS
1
Online
View Details

ENVIRONMENT STATUS
Normal
View Details

POWER STATUS
Normal
View Details

DOOR STATUS
Closed
View Details

ALERTS
0
Active
View Details

SMART RACK VIEW



ENVIRONMENT OVERVIEW

Temperature
23.4 °C
Normal

Humidity
45 %RH
Normal

Smoke
Normal
No Smoke

Water Leak
Dry
No Leak

Door Status
Closed
Secure

Airflow Status
Normal
Good

POWER OVERVIEW

Input Voltage
229 V
Normal

Load Level
38 %
Normal

UPS Status
Online
Normal

Battery Capacity
100 %
Normal

Estimated Runtime
72 min
@ Current Load

DEVICE STATUS LIST

Device Name	Type	Status	Last Update
Smart Rack (SC-C03JED-IT01)	Smart Rack	Online	10:25:12 AM
PDU-01	PDU	Online	10:25:10 AM
UPS-01	UPS	Online	10:25:11 AM
Environment Sensor	Sensor	Normal	10:25:12 AM
Cooling Unit	ACU	Normal	10:25:09 AM
Network Switch	Switch	Online	10:25:10 AM

EVENT / ALERT LOG (RECENT)

Time	Event	Device	Severity	Status
10:24:15 AM	Door Closed	Smart Rack	Info	Cleared
10:20:31 AM	Temperature Normal	Environment Sensor	Info	Cleared
10:15:07 AM	Power Restored	PDU-01	Info	Cleared
10:10:44 AM	Door Opened	Smart Rack	Info	Cleared
10:05:21 AM	Temperature High	Environment Sensor	Warning	Cleared
10:02:10 AM	Smoke Normal	Smoke Sensor	Info	Cleared

SYSTEM INFORMATION

System Type	Smart Rack System
Manufacturer	Vertiv
Model	SmartCabinet™ Premium
Cabinet ID	SC-C03JED-IT01
Location	Ground Floor - IT Room
Installation Date	Jan 10, 2026
Firmware Version	v3.2.1
Monitoring Protocol	SNMP / Modbus
Last Update	10:25:12 AM
System Status	Normal

SELECTED DEVICE DETAILS

Rack: SC-C03JED-IT01	
Device Type	Smart Rack
IP Address	10.10.0.1
MAC Address	00:1A:2B:3C:4D:5E
Serial Number	RACKA123456789
Uptime	15d 04:32:11
Monitored By	BMS
Status	Online

VIEW DEVICE DETAILS

ACTIVE ALARMS

Time	Device	Alarm	Severity	Status
No Active Alarms				

VIEW ALARMS HISTORY

QUICK ACTIONS



Device Details



Environment Trends



Power Trends



Network Map



Event History



Configuration